

Python Code Documentation

Apolline Boyer

August 1, 2024

Contents

1	Classes and Functions	3
1.1	Class StereoCalibration	3
1.1.1	Method __str__	3
1.1.2	Method __init__	3
1.1.3	Method save_data	4
1.1.4	Method rectify	4
1.1.5	Method load_data	4
1.2	Class Calibrator	5
1.2.1	Method __init__	5
1.2.2	Method corner_detect	5
1.2.3	Method calibrate_camera	6
1.2.4	Method calibration_process	6
1.3	Class DualCameraCapture	6
1.3.1	Method __init__	7
1.3.2	Method capture_and_save_image	7
1.3.3	Method display_images	7
1.3.4	Method validate_images	8
1.3.5	Method capture_images	8
1.4	Class StereoVision	8
1.4.1	Method __init__	9
1.4.2	Method stereo_taking	10
1.4.3	Method save_images	10
1.4.4	Method depth_map_calcul	10
1.4.5	Method depth_calcul	10
1.4.6	Method process_stereo	11
1.4.7	Method capture_and_compute	11
1.4.8	Method depth_map_display	11
1.4.9	Method process_and_display	11
1.5	Class TofCamera	12
1.5.1	Method __init__	12
1.5.2	Method process_frame	12
1.5.3	Method capture_image	13

1.5.4	Method <code>process_tof</code>	13
1.5.5	Method <code>continuous_display</code>	13
1.5.6	Method <code>cleanup</code>	13
1.5.7	Method <code>get_depth_buf</code>	14
1.5.8	Method <code>get_depth_normalized</code>	14
1.6	Class <code>DepthMapProcessor</code>	14
1.6.1	Method <code>__init__</code>	15
1.6.2	Method <code>apply_morphological_operations</code>	15
1.6.3	Method <code>calculate_mean_amplitude</code>	15
1.6.4	Method <code>find_and_draw_contours</code>	16
1.6.5	Method <code>process_contour</code>	16
1.6.6	Method <code>process_disparity_image</code>	16
1.7	Utility Functions	17
1.7.1	Function <code>calculate_histogram</code>	17
1.7.2	Function <code>count_non_zero_pixels_from_histogram</code>	17
1.7.3	Function <code>plot_histogram</code>	17
2	Functions	18
2.1	Function <code>folder_create</code>	18
2.2	Function <code>file_create</code>	18
2.3	Function <code>show_image</code>	18
2.3.1	List of Colormaps	19
3	Camera and Process Management	19
3.1	Function <code>calibrate_cameras</code>	19
3.2	Function <code>run_tof_camera</code>	20
3.3	Function <code>run_stereo_vision</code>	20
3.4	Function <code>terminate_processes</code>	20
3.5	Function <code>kill_zombie_processes</code>	20
3.6	Function <code>clean_temp_dirs</code>	21
3.7	Function <code>cleanup</code>	21
4	Main Script Execution	21

1 Classes and Functions

1.1 Class StereoCalibration

- **Description:** This class manages the parameters and processes of stereo calibration for two cameras.
- **Attributes:**
 - `cam_mats`: Dictionary of camera matrices (intrinsic parameters) for the left and right cameras.
 - `dist_coefs`: Dictionary of distortion coefficients for the left and right cameras.
 - `rot_mat`: Rotation matrix.
 - `trans_vec`: Translation vector.
 - `e_mat`: Essential matrix.
 - `f_mat`: Fundamental matrix.
 - `rect_trans`: Dictionary of rectification transformations for the left and right cameras.
 - `proj_mats`: Dictionary of projection matrices for the left and right cameras.
 - `disp_to_depth_mat`: Disparity-to-depth conversion matrix.
 - `valid_boxes`: Dictionary of valid pixel bounding boxes for the left and right cameras.
 - `undistortion_map`: Dictionary of undistortion maps for the left and right cameras.
 - `rectification_map`: Dictionary of rectification maps for the left and right cameras.

1.1.1 Method `__str__`

- **Description:** Returns a string representation of the class attributes.
- **Arguments:** None.
- **Returns:** `str` - String representation of the object's attributes.
- **Usage Example:**

```
1 print(calibration)
```

1.1.2 Method `__init__`

- **Description:** Initializes the calibration parameters for stereo cameras.
- **Arguments:** None.
- **Returns:** None.

- **Usage Example:**

```
1 calibration = StereoCalibration()
```

1.1.3 Method `save_data`

- **Description:** Saves the calibration parameters to .npy and .csv files.
- **Arguments:** None.
- **Returns:** None.
- **Usage Example:**

```
1 calibration.save_data()
```

1.1.4 Method `rectify`

- **Description:** Rectifies stereo images using undistortion and rectification maps.
- **Arguments:**
 - **frames:** **list** - List of left and right camera images.
- **Returns:** **list** - List of rectified images.
- **Usage Example:**

```
1 rectified_frames = calibration.rectify(frames)
```

1.1.5 Method `load_data`

- **Description:** Loads calibration parameters from .npy files in a specified directory.
- **Arguments:**
 - **directory:** **str** - Directory containing the parameter files.
- **Returns:** None.
- **Usage Example:**

```
1 calibration.load_data('calibration_data')
```

1.2 Class Calibrator

- **Description:** Manages the calibration process for a pair of stereo cameras.
- **Attributes:**
 - `image_count`: Number of calibration images used.
 - `row`: Number of internal corners in the rows of the calibration pattern.
 - `column`: Number of internal corners in the columns of the calibration pattern.
 - `square_size`: Size of the calibration pattern squares in cm.
 - `image_size`: Size of calibration images in pixels.
 - `corner_coordinates`: 3D coordinates of the calibration pattern corners.
 - `object_points`: List of coordinates of real corners found in each image.
 - `image_points`: Dictionary of coordinates of corners found in the images for the left and right cameras.

1.2.1 Method `__init__`

- **Description:** Initializes the parameters for camera calibration.
- **Arguments:**
 - `row`: **int** - Number of internal corners in the rows of the pattern.
 - `column`: **int** - Number of internal corners in the columns of the pattern.
 - `square_size`: **float** - Size of the pattern squares in cm.
 - `image_size`: **tuple** - Size of calibration images in pixels.
- **Returns:** None.
- **Usage Example:**

```
1 calibrator = Calibrator(row=6, column=9, square_size=2.5,  
    image_size=(1920, 1080))
```

1.2.2 Method `corner_detect`

- **Description:** Detects the corners of the calibration pattern in a pair of images.
- **Arguments:**
 - `image_pair`: **tuple** - Tuple containing the left and right images.
- **Returns:** None.
- **Usage Example:**

```
1 calibrator.corner_detect((left_image, right_image))
```

1.2.3 Method `calibrate_camera`

- **Description:** Calibrates both cameras and determines their related matrices.
- **Arguments:** None.
- **Returns:** **StereoCalibration** - Instance of the **StereoCalibration** class with calibrated parameters.
- **Usage Example:**

```
1 calibration = calibrator.calibrate_camera()
```

1.2.4 Method `calibration_process`

- **Description:** Performs the calibration process by reading the calibration images and calling the calibration method.
- **Arguments:**
 - **nbr_photo:** **int** - Number of calibration images to process.
 - **image_folder:** **str** - Directory containing the calibration images.
- **Returns:** **StereoCalibration** - Instance of the **StereoCalibration** class with the calibrated parameters.
- **Usage example:**

```
1 calibration = calibrator.calibration_process(nbr_photo=20,  
    image_folder='calibration_images')
```

1.3 Class `DualCameraCapture`

- **Description:** Captures stereo images using two cameras and provides tools to display and validate these images.
- **Attributes:**
 - **left_cam_id:** ID of the left camera.
 - **right_cam_id:** ID of the right camera.
 - **preview_size:** Size of the preview of the captured images.
 - **preview_type:** Type of preview.
 - **capture_delay:** Delay before capturing the image.
 - **interval:** Interval between image captures.

1.3.1 Method `__init__`

- **Description:** Initializes the parameters for capturing images with two cameras.
- **Arguments:**
 - `left_cam_id`: **int** - ID of the left camera.
 - `right_cam_id`: **int** - ID of the right camera.
 - `preview_size`: **tuple** - Size of the preview.
 - `preview_type`: **Preview** - Type of preview.
 - `capture_delay`: **float** - Delay before capturing the image.
 - `interval`: **float** - Interval between image captures.
- **Returns:** None.
- **Usage example:**

```
1 capture = DualCameraCapture(left_cam_id=0, right_cam_id=1,  
    preview_size=(800, 600), capture_delay=2, interval=5)
```

1.3.2 Method `capture_and_save_image`

- **Description:** Captures and saves an image from the specified camera.
- **Arguments:**
 - `picam_id`: **int** - ID of the camera to use.
 - `filename`: **str** - Filename to save the image.
- **Returns:** None.
- **Usage example:**

```
1 capture.capture_and_save_image(picam_id=0, filename='left_image.png'  
    ,')
```

1.3.3 Method `display_images`

- **Description:** Displays the captured images from the specified files.
- **Arguments:**
 - `left_filename`: **str** - Filename of the left image.
 - `right_filename`: **str** - Filename of the right image.
- **Returns:** None.
- **Usage example:**

```
1 capture.display_images(left_filename='left_image.png',  
    right_filename='right_image.png')
```

1.3.4 Method `validate_images`

- **Description:** Validates if the captured images are acceptable.
- **Arguments:** None.
- **Returns:** `bool` - Returns True if the images are acceptable, otherwise False.
- **Usage example:**

```
1 is_valid = capture.validate_images()
```

1.3.5 Method `capture_images`

- **Description:** Captures a specified number of image pairs and saves them in the specified folder.
- **Arguments:**
 - `nbr_photos`: `int` - Number of image pairs to capture.
 - `image_folder`: `str` - Folder to save the images.
- **Returns:** None.
- **Usage example:**

```
1 capture.capture_images(nbr_photos=10, image_folder='captured_images',)
```

1.4 Class `StereoVision`

- **Description:** This class manages stereo image capture, disparity and depth map calculation, as well as result processing and display.
- **Attributes:**
 - `cam_capture`: Instance of `DualCameraCapture` used for capturing images.
 - `baseline`: Distance between the cameras (in meters).
 - `focal`: Focal length of the camera.
 - `block_size`: Block size for stereo matching.
 - `P1`: Weight for cost regularization.
 - `P2`: Weight for cost regularization.
 - `min_disp`: Minimum disparity to consider.
 - `max_disp`: Maximum disparity to consider.
 - `uniqueRatio`: Uniqueness ratio for stereo matching.
 - `speckleWindowSize`: Window size for speckle filtering.
 - `speckleRange`: Range of values for speckle filtering.

- `disp12MaxDiff`: Maximum difference between left and right disparities.
- `stop_event`: Event to stop processes.
- `n`: Counter for the number of saved images.
- `images`: Dictionary to store captured and rectified images.
- `disparity`: Calculated disparity map.
- `disparity_normalized`: Normalized disparity map for display.
- `depth`: Calculated depth map.

1.4.1 Method `__init__`

- **Description:** Initializes the parameters for stereo vision.
- **Arguments:**
 - `cam_capture`: **DualCameraCapture** - Instance of the class for capturing images.
 - `baseline`: **float** - Distance between the cameras.
 - `focal`: **float** - Focal length of the camera.
 - `block_size`: **int** - Block size for stereo matching.
 - `P1`: **int** - Weight for cost regularization.
 - `P2`: **int** - Weight for cost regularization.
 - `min_disp`: **int** - Minimum disparity to consider.
 - `max_disp`: **int** - Maximum disparity to consider.
 - `uniqueRatio`: **int** - Uniqueness ratio for stereo matching.
 - `speckleWindowSize`: **int** - Window size for speckle filtering.
 - `speckleRange`: **int** - Range of values for speckle filtering.
 - `disp12MaxDiff`: **int** - Maximum difference between left and right disparities.
- **Returns:** None.
- **Usage example:**

```

1 stereo_vision = StereoVision(
2     cam_capture=DualCameraCapture(left_cam_id=0, right_cam_id=1,
3     preview_size=(800, 600)),
4     baseline=0.06,
5     focal=1300,
6     block_size=15,
7     P1=150,
8     P2=64,
9     min_disp=-16,
10    max_disp=128,
11    uniqueRatio=4,
12    speckleWindowSize=200,
13    speckleRange=4,
14    disp12MaxDiff=0
15 )

```

1.4.2 Method stereo_taking

- **Description:** Captures and rectifies stereo images.
- **Arguments:** None.
- **Returns:** None.
- **Usage example:**

```
1 stereo_vision.stereo_taking()
```

1.4.3 Method save_images

- **Description:** Saves the images and the normalized disparity map.
- **Arguments:** None.
- **Returns:** None.
- **Usage example:**

```
1 stereo_vision.save_images()
```

1.4.4 Method depth_map_calcul

- **Description:** Calculates the disparity map from the rectified images.
- **Arguments:** None.
- **Returns:** None.
- **Usage example:**

```
1 stereo_vision.depth_map_calcul()
```

1.4.5 Method depth_calcul

- **Description:** Calculates the depth for each pixel from the disparity map.
- **Arguments:** None.
- **Returns:** None.
- **Usage example:**

```
1 stereo_vision.depth_calcul()
```

1.4.6 Method `process_stereo`

- **Description:** Processes the depth map using `DepthMapProcessor`.
- **Arguments:** None.
- **Returns:** None.
- **Usage example:**

```
1 stereo_vision.process_stereo()
```

1.4.7 Method `capture_and_compute`

- **Description:** Captures images, calculates the disparity map and depth, and then puts the results in a queue.
- **Arguments:**
 - queue: **Queue** - Queue for passing results between processes.
- **Returns:** None.
- **Usage example:**

```
1 queue = Queue()
2 stereo_vision.capture_and_compute(queue)
```

1.4.8 Method `depth_map_display`

- **Description:** Displays the disparity map and depth from the results in the queue.
- **Arguments:**
 - queue: **Queue** - Queue for obtaining calculated results.
- **Returns:** None.
- **Usage example:**

```
1 queue = Queue()
2 stereo_vision.depth_map_display(queue)
```

1.4.9 Method `process_and_display`

- **Description:** Creates processes for capturing and computing images, as well as displaying the results.
- **Arguments:** None.
- **Returns:** None.
- **Usage example:**

```
1 stereo_vision.process_and_display()
```

1.5 Class TofCamera

- **Description:** This class handles capturing images from a ToF camera, processing depth and amplitude data, and displaying the results.
- **Attributes:**
 - `cam`: Instance of `ArducamCamera` for the ToF camera.
 - `max_distance`: Maximum measurable distance by the camera (in meters).
 - `frame`: Current frame captured by the camera.
 - `amplitude_buf`: Buffer for amplitude data.
 - `depth_buf`: Buffer for depth data.
 - `depth_normalized`: Normalized depth map for display.
 - `result_image`: Resulting image after processing.
 - `n`: Counter for saved image names.

1.5.1 Method `__init__`

- **Description:** Initializes the ToF camera with the maximum distance parameters.
- **Arguments:**
 - `max_distance`: `float` - Maximum measurable distance by the camera (in meters).
- **Returns:** None.
- **Usage example:**

```
1 tof_camera = TofCamera(max_distance=4)
```

1.5.2 Method `process_frame`

- **Description:** Processes the captured frame to produce a resulting image by combining depth and amplitude data.
- **Arguments:** None.
- **Returns:** `np.ndarray` - Resulting image after processing.
- **Usage example:**

```
1 result_image = tof_camera.process_frame()
```

1.5.3 Method `capture_image`

- **Description:** Saves the resulting image under the name `tof{n}.png`.
- **Arguments:** None.
- **Returns:** None.
- **Usage example:**

```
1 tof_camera.capture_image()
```

1.5.4 Method `process_tof`

- **Description:** Processes the depth map using `DepthMapProcessor` to analyze and extract contours.
- **Arguments:** None.
- **Returns:** None.
- **Usage example:**

```
1 tof_camera.process_tof()
```

1.5.5 Method `continuous_display`

- **Description:** Captures and displays images continuously from the ToF camera, with options to save and process images.
- **Arguments:** None.
- **Returns:** None.
- **Usage example:**

```
1 tof_camera.continuous_display()
```

1.5.6 Method `cleanup`

- **Description:** Stops and closes the camera, and destroys all OpenCV windows.
- **Arguments:** None.
- **Returns:** None.
- **Usage example:**

```
1 tof_camera.cleanup()
```

1.5.7 Method `get_depth_buf`

- **Description:** Returns the current depth buffer.
- **Arguments:** None.
- **Returns:** `np.ndarray` - Depth buffer.
- **Usage example:**

```
1 depth_buf = tof_camera.get_depth_buf()
```

1.5.8 Method `get_depth_normalized`

- **Description:** Returns the normalized depth map.
- **Arguments:** None.
- **Returns:** `np.ndarray` - Normalized depth map.
- **Usage example:**

```
1 depth_normalized = tof_camera.get_depth_normalized()
```

1.6 Class `DepthMapProcessor`

- **Description:** This class handles processing of depth and disparity maps, including segmentation, calculating average amplitudes, and drawing contours.
- **Attributes:**
 - `depth_map_original`: Original depth map.
 - `depth_map_normalized`: Normalized disparity map.
 - `pixel_min`: Minimum number of non-zero pixels required to consider a segment (default 15000).
 - `min_contour_area`: Minimum area for contours to be considered (default 10).
 - `thresholds`: List of thresholds for disparity segmentation.
 - `kernel_size`: Kernel size for morphological operations (default 5).
 - `dilate_iterations`: Number of iterations for dilation (default 1).
 - `erode_iterations`: Number of iterations for erosion (default 2).
 - `segmented_image`: Segmented image after applying thresholds.
 - `contours`: List of found contours.
 - `mean_amplitudes`: Dictionary of average amplitudes for each contour.

1.6.1 Method `__init__`

- **Description:** Initializes the `DepthMapProcessor` class with the provided parameters.
- **Arguments:**
 - `depth_map`: `np.ndarray` - Original depth map.
 - `disparity`: `np.ndarray` - Normalized disparity map.
 - `pixel_min`: `int` - Minimum number of non-zero pixels required to consider a segment (default 15000).
 - `min_contour_area`: `int` - Minimum area for contours to be considered (default 10).
 - `thresholds`: `list` - List of thresholds for disparity segmentation.
 - `kernel_size`: `int` - Kernel size for morphological operations (default 5).
 - `dilate_iterations`: `int` - Number of iterations for dilation (default 1).
 - `erode_iterations`: `int` - Number of iterations for erosion (default 2).
- **Returns:** None.
- **Usage example:**

```
1 depth_map = np.zeros((480, 640)) # Example depth map
2 disparity = np.zeros((480, 640)) # Example disparity map
3 processor = DepthMapProcessor(depth_map, disparity)
```

1.6.2 Method `apply_morphological_operations`

- **Description:** Applies morphological operations (dilation and erosion) to the specified image.
- **Arguments:**
 - `image`: `np.ndarray` - Image to process.
- **Returns:** `np.ndarray` - Image after applying morphological operations.
- **Usage example:**

```
1 processed_image = processor.apply_morphological_operations(image)
```

1.6.3 Method `calculate_mean_amplitude`

- **Description:** Calculates the average amplitude for each specified contour.
- **Arguments:**
 - `contours`: `list` - List of contours found in the image.

- **Returns:** `dict` - Dictionary of average amplitudes for each contour.
- **Usage example:**

```
1 mean_amplitudes = processor.calculate_mean_amplitude(contours)
```

1.6.4 Method `find_and_draw_contours`

- **Description:** Finds and draws contours in the processed image.
- **Arguments:**
 - `processed_image`: `np.ndarray` - Image after morphological operations.
- **Returns:** `np.ndarray` - Image with drawn contours.
- **Usage example:**

```
1 image_with_contours = processor.find_and_draw_contours(
    processed_image)
```

1.6.5 Method `process_contour`

- **Description:** Processes contours by applying morphological operations, finding and drawing contours, and calculating average amplitudes for the found contours.
- **Arguments:** None.
- **Returns:** None.
- **Usage example:**

```
1 processor.process_contour()
```

1.6.6 Method `process_disparity_image`

- **Description:** Processes the disparity image by segmenting it according to the defined thresholds, and then applying contour processing on each segment.
- **Arguments:** None.
- **Returns:** None.
- **Usage example:**

```
1 processor.process_disparity_image()
```


1.7 Utility Functions

1.7.1 Function `calculate_histogram`

- **Description:** Calculates the histogram of pixel values in the image.
- **Arguments:**
 - `image`: `np.ndarray` - Image to analyze.
- **Returns:** `np.ndarray` - Histogram of pixel values.
- **Usage example:**

```
1 hist = calculate_histogram(image)
```

1.7.2 Function `count_non_zero_pixels_from_histogram`

- **Description:** Counts the number of non-zero pixels from the pixel value histogram.
- **Arguments:**
 - `hist`: `np.ndarray` - Histogram of pixel values.
- **Returns:** `int` - Total number of non-zero pixels.
- **Usage example:**

```
1 non_zero_count = count_non_zero_pixels_from_histogram(hist)
```

1.7.3 Function `plot_histogram`

- **Description:** Plots and displays the histogram of pixel values.
- **Arguments:**
 - `title`: `str` - Title of the plot.
 - `hist`: `np.ndarray` - Histogram of pixel values.
- **Returns:** `None`.
- **Usage example:**

```
1 plot_histogram("Pixel Histogram", hist)
```

2 Functions

2.1 Function `folder_create`

- **Description:** Checks if a folder exists; if not, it creates one.
- **Arguments:**
 - `folder`: **str** - Path of the folder to check/create.
- **Returns:** None.
- **Usage example:**

```
1 folder_create('path/to/folder')
```

2.2 Function `file_create`

- **Description:** Creates a file of the specified type in a given folder (optional).
- **Arguments:**
 - `data`: **np.ndarray**, **list**, or other - Data to save in the file.
 - `file_name`: **str** - Name of the file to create (without extension).
 - `file_type`: **str** - Type of file to create ('csv', 'image', 'numpy', etc.).
 - `folder_name`: **str** (optional) - Folder in which to create the file.
- **Returns:** None.
- **Usage example:**

```
1 file_create(data, 'example_image', 'png', 'path/to/folder')
2 file_create(data, 'example_array', 'numpy')
3 file_create(data, [['header1', 'header2'], [1, 2]], 'csv', 'path/to
  /folder')
```

2.3 Function `show_image`

- **Description:** Displays an image with a specified colormap.
- **Arguments:**
 - `title`: **str** - Title of the display window.
 - `image`: **np.ndarray** - Image to display.
 - `cmap`: **str** (optional) - OpenCV colormap to apply ('gray', 'jet', 'rainbow', etc.).
- **Returns:** None.
- **Usage example:**

```
1 show_image('Displayed Image', image, 'jet')
```

2.3.1 List of Colormaps

- **Available Colormaps:**

- autumn
- bone
- jet
- winter
- rainbow
- ocean
- summer
- spring
- cool
- hsv
- pink
- hot
- parula
- magma
- inferno
- plasma
- viridis
- cividis
- twilight
- twilight_shifted
- turbo
- deepgreen

3 Camera and Process Management

3.1 Function `calibrate_cameras`

- **Description:** Calibrates the cameras by taking pictures of a checkerboard and using a calibration process.
- **Arguments:**
 - `cam_capture`: Instance of `DualCameraCapture` for capturing images.
- **Returns:** None.
- **Usage example:**

```
1 calibrate_cameras(cam_capture)
```

3.2 Function `run_tof_camera`

- **Description:** Function to run the ToF camera continuously and update a queue with depth data.
- **Arguments:**
 - `camera_queue`: Queue to store camera data.
- **Returns:** None.
- **Usage example:**

```
1 run_tof_camera(camera_queue)
```

3.3 Function `run_stereo_vision`

- **Description:** Function to run stereo vision and return the disparity and depth results.
- **Arguments:** None.
- **Returns:** Tuple containing normalized disparity and depth.
- **Usage example:**

```
1 disparity_normalized, depth = run_stereo_vision()
```

3.4 Function `terminate_processes`

- **Description:** Terminates the given processes.
- **Arguments:**
 - `processes`: List of processes to terminate.
- **Returns:** None.
- **Usage example:**

```
1 terminate_processes(processes)
```

3.5 Function `kill_zombie_processes`

- **Description:** Terminates the zombie processes detected on the system.
- **Arguments:** None.
- **Returns:** None.
- **Usage example:**

```
1 kill_zombie_processes()
```

3.6 Function clean_temp_dirs

- **Description:** Cleans the specified temporary directories.
- **Arguments:**
 - **directories:** List of directories to clean.
- **Returns:** None.
- **Usage example:**

```
1 clean_temp_dirs(['/tmp', '/var/tmp'])
```

3.7 Function cleanup

- **Description:** Performs system cleanup and frees memory.
- **Arguments:** None.
- **Returns:** None.
- **Usage example:**

```
1 cleanup()
```

4 Main Script Execution

```
1 if __name__ == "__main__":
2     cleanup()
3     folder_create('data')
4     folder_create('image')
5     folder_create('corner')
6
7     calib_choice = input("Do you want to calibrate the cameras (y/n)? ")
8     .strip().lower()
9
10    if calib_choice == "y":
11        cam_capture = DualCameraCapture(left_cam_id=2, right_cam_id=1,
12            preview_size=(840, 820))
13        calibrate_cameras(cam_capture)
14    elif calib_choice == "n":
15        print("Cameras will not be calibrated.")
16    else:
17        print("Invalid choice. Please enter 'y' or 'n'.")
18        exit(1)
19
20    # Initialize queues for inter-process communication
21    camera_queue = multiprocessing.Queue()
22
23    # Create processes
24    tof_process = multiprocessing.Process(target=run_tof_camera, args=(
25        camera_queue,))
```

```

23 stereo_process = multiprocessing.Process(target=run_stereo_vision)
24
25 # Start processes
26 tof_process.start()
27 stereo_process.start()
28
29 processes = [tof_process, stereo_process]
30
31 # Wait for processes to finish
32 try:
33     # Keep processes alive
34     while True:
35         sleep(1)
36 except KeyboardInterrupt:
37     print("Interruption detected. Stopping processes...")
38 finally:
39     # Stop processes
40     terminate_processes(processes)
41     print("All processes have been stopped.")
42     cleanup()
43     sys.exit(0)

```